

System.MemberAccessException Class

```
[ILAsm]
.class public serializable MemberAccessException extends
System.SystemException

[C#]
public class MemberAccessException: SystemException
```

Assembly Info:

- *Name:* mscorlib
- *Public Key:* [00 00 00 00 00 00 00 00 04 00 00 00 00 00 00]
- *Version:* 2.0.x.x
- *Attributes:*
 - CLSCompliantAttribute(true)

Summary

`System.MemberAccessException` is the base class for exceptions that occurs when an attempt to locate or access a type member fails.

Inherits From: System.SystemException

Library: RuntimeInfrastructure

Thread Safety: All public static members of this type are safe for multithreaded operations. No instance members are guaranteed to be thread safe.

Description

[*Note:* `System.MemberAccessException` exceptions are typically thrown by the system when members in a class library have been changed or removed, and an assembly that references the class library has not been recompiled.

The Base Class Library includes the following derived types:

- `System.FieldAccessException`
- `System.MethodAccessException`
- `System.MissingMemberException`

When appropriate, use these types instead of `System.MemberAccessException`.

]

MemberAccessException() Constructor

```
[ILAsm]  
public rtspecialname specialname instance void .ctor()
```

```
[C#]  
public MemberAccessException()
```

Summary

Constructs and initializes a new instance of the `System.MemberAccessException` class.

Description

This constructor initializes the `System.MemberAccessException.Message` property of the new instance to a system-supplied message that describes the error, such as "Cannot access member." This message takes into account the current system culture.

The `System.MemberAccessException.InnerException` property of the new instance is initialized to `null`.

MemberAccessException(System.String) Constructor

```
[ILAsm]  
public rtspecialname specialname instance void .ctor(string message)  
  
[C#]  
public MemberAccessException(string message)
```

Summary

Constructs and initializes a new instance of the `System.MemberAccessException` class.

Parameters

Parameter	Description
<i>message</i>	A <code>System.String</code> that describes the error. The content of <i>message</i> is intended to be understood by humans. The caller of this constructor is required to ensure that this string has been localized for the current system culture.

Description

This constructor initializes the `System.MemberAccessException.Message` property of the new instance using *message*. If *message* is `null`, the `System.MemberAccessException.Message` property is initialized to the system-supplied message provided by the constructor that takes no arguments.

The `System.MemberAccessException.InnerException` property of the new instance is initialized to `null`.

MemberAccessException(System.String, System.Exception) Constructor

```
[ILAsm]  
public rtspecialname specialname instance void .ctor(string message,  
class System.Exception inner)
```

```
[C#]  
public MemberAccessException(string message, Exception inner)
```

Summary

Constructs and initializes a new instance of the `System.MemberAccessException` class.

Parameters

Parameter	Description
<i>message</i>	A <code>System.String</code> that describes the error. The content of <i>message</i> is intended to be understood by humans. The caller of this constructor is required to ensure that this string has been localized for the current system culture.
<i>inner</i>	An instance of <code>System.Exception</code> that is the cause of the current exception. If <i>inner</i> is not a null reference, then the current <code>System.Exception</code> was raised in a catch block handling <i>inner</i> .

Description

This constructor initializes the `System.MemberAccessException.Message` property of the new instance using *message* and the `System.MemberAccessException.InnerException` property using *inner*. If *message* is null, the `System.MemberAccessException.Message` property is initialized to the system-supplied message provided by the constructor that takes no arguments.

[*Note:* For more information on inner exceptions, see `System.Exception.InnerException`.]