

System.NullReferenceException Class

```
[ILAsm]  
.class public serializable NullReferenceException extends  
System.SystemException
```

```
[C#]  
public class NullReferenceException: SystemException
```

Assembly Info:

- *Name:* mscorlib
- *Public Key:* [00 00 00 00 00 00 00 00 04 00 00 00 00 00 00]
- *Version:* 2.0.x.x
- *Attributes:*
 - CLSCompliantAttribute(true)

Summary

Represents the error that occurs when there is an attempt to dereference a null object reference.

Inherits From: System.SystemException

Library: BCL

Thread Safety: All public static members of this type are safe for multithreaded operations. No instance members are guaranteed to be thread safe.

Description

[*Note:* Applications throw the `System.ArgumentNullException` rather than `System.NullReferenceException`.

The following CIL instructions throw `System.NullReferenceException`:

- callvirt
- cpblk
- cpobj
- ldelema
- ldelem.<type>
- ldfld

- ldflda
- ldind.<type>
- ldlen
- stelem.<type>
- stind.<type>
- stfld
- throw
- unbox
- initblk

]

Example

The following example demonstrates an error that causes a `System.NullReferenceException` exception.

[C#]

```
using System;
public class Ints {
    public int[] myInts;
}
public class NullRefExample {
    public static void Main() {
        Ints ints = new Ints();
        try {
            int i = ints.myInts[0];
        }
        catch( NullReferenceException e ) {
            Console.WriteLine( "Caught error: {0}.", e);
        }
    }
}
```

The output is

```
Caught error: System.NullReferenceException: Object reference not set
to an instance of an object.
   at NullRefExample.Main().
```

NullReferenceException() Constructor

```
[ILAsm]  
public rtspecialname specialname instance void .ctor()  
  
[C#]  
public NullReferenceException()
```

Summary

Constructs and initializes a new instance of the `System.NullReferenceException` class.

Description

This constructor initializes the `System.NullReferenceException.Message` property of the new instance to a system-supplied message that describes the error, such as "The value 'null' was found where an instance of an object was required." This message takes into account the current system culture.

The `System.NullReferenceException.InnerException` property is initialized to `null`.

NullReferenceException(System.String) Constructor

```
[ILAsm]  
public rtspecialname specialname instance void .ctor(string message)  
  
[C#]  
public NullReferenceException(string message)
```

Summary

Constructs and initializes a new instance of the `System.NullReferenceException` class.

Parameters

Parameter	Description
<i>message</i>	A <code>System.String</code> that describes the error. The content of <i>message</i> is intended to be understood by humans. The caller of this constructor is required to ensure that this string has been localized for the current system culture.

Description

This constructor initializes the `System.NullReferenceException.Message` property of the new instance using *message*. If *message* is null, the `System.NullReferenceException.Message` property is initialized to the system-supplied message provided by the constructor that takes no arguments. The `System.NullReferenceException.InnerException` property is initialized to null.

NullReferenceException(System.String, System.Exception) Constructor

```
[ILAsm]
public rtspecialname specialname instance void .ctor(string message,
class System.Exception innerException)

[C#]
public NullReferenceException(string message, Exception
innerException)
```

Summary

Constructs and initializes a new instance of the System.NullReferenceException class.

Parameters

Parameter	Description
<i>message</i>	A System.String that describes the error. The content of <i>message</i> is intended to be understood by humans. The caller of this constructor is required to ensure that this string has been localized for the current system culture.
<i>innerException</i>	An instance of System.Exception that is the cause of the current Exception. If <i>innerException</i> is non-null, then the current Exception was raised in a catch block handling <i>innerException</i> .

Description

This constructor initializes the System.NullReferenceException.Message property of the new instance using *message*, and the System.NullReferenceException.InnerException property using *innerException*. If *message* is null, the System.NullReferenceException.Message property is initialized to the system-supplied message provided by the constructor that takes no arguments.

[*Note:* For information on inner exceptions, see System.Exception.InnerException.]